

## **DBU RDB Documentation**

To use DBURDB you must first start the DBURDB subsystem, and then configure the remote connections you wish to use. To start the DBURDB subsystem, from a System i command line execute the command **STRSBS SBSD(DBURDBSBS)**. You will have at least one RDBWORKER job running in the subsystem.

To start configuring DBURDB, from a System i command line execute the command **DBURDBCFG**. This will take you to the **Manage Remote Systems** screen.

		Manage	e Remote Syst	ems			
Job Status:		ive	Java Versi	on: F	ress F22	to display	
Turn Tracing On:			Trace Type	<u>A</u> F	All E=Eri	rors Only	
Server port nu	mber.: <mark>908</mark>	3					
Java Version	: <u>1.6</u>	<u> </u>					
Log File Size.	.: 38	KB					
Log Size Max	.: 128	MB					
Tune Ontion D	nore Entor						
1=Undate 4=Del	oto 5=Dicr	lau 7=Ed	it Authoritu	8=Table	e 9=Tect (	Connection	
OPT RDB Name	DB Tupe	Remote	Connection D	escript	ion	Johnee (10)	
MSSQLTEST	MSSQL	MSSQL [	DB				
MSSQL16	MSSQL	MSSQL 2	2016 Demo DB				
E1=Help E3=Exi	t E6=Add E	7=Tracelo	na E8=IES E26	Fnd Jo	b 21=Clea	loas	
II HELP IO EXI		i iideett	5g 10 110 120			LOGO	

**Number of RDB Jobs** – The initial number of **RDBWORKE**R jobs to run. The default number of jobs is 1. A **RDBWORKER** job is needed for each concurrent user that connects to a remote database.

**Turn Tracing On** – Default is N. Set to Y when troubleshooting with ProData Tech Support. The DBURDBSBS subsystem must be restarted for this value to take effect.

**RDB Connect Timeout** – The number of seconds elapsed before a connection attempt to the remote system will occur.

Press **F6** to add a remote connection.

: 🛃 🔁 🕖 💷 🆏 🐻 🔡 🕮 🗰 💥 🔹 🚢 📸 🚆 🕖 👁		
Manage Bemete Sustems		
Manage Remote Systems		
Remote Database ID:		
Database Type: (F4=Prompt)		
1/P Address:		
Port #		
Catalog/Service:	(F4=Prompt)	
Schema	(F4=Prompt)	
User Name:		
Decuard		
F1=Help F3=Exit F4=Prompt F6=Save F12=Return		
		04/02

Enter the information for the remote database.

**Remote Database ID** – This is the name that will be used when referencing this database connection.

**Description** – The description for this remote connection.

Database Type – The type of database being configured

**I/P Address** – The I/P address used to access the remote database.

**Port** *#* – The port number to be used with the above I/P address to connect to the remote database. If using the default port for the specified database type, this can be left blank. When in doubt, specify the port number.

**Catalog/Service** – Some databases require a Catalog or Service to be specified on the connection. If one is required for the database specified, enter it here.

**Schema** – The schema for the remote database.

User Name – The user to be used when connecting. This user id will control the authority on the remote database when using this connection. This user name must be configured on the remote database.

**Password** – The password for the above entered user name.

To save the information, **press F6**. The information entered will be encrypted 256 bit and stored in a System i object. The object will be named the same as the **Remote Database ID** and be placed in the DBU library. System i object level authority can be used, with this object, to add another level of security to the remote connection.

a n n n 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1		
Manage Remote Systems		
Remote Database ID: <u>MSSQL16</u>		
Description: MSSQL 2016 Demo DB		
Database Type: <u>MSSQL</u> (F4=Prompt)		
I/P Address: <u>64.253.187.230</u>		
Port # <u>1433</u>		
Catalog/Service: <u>AdventureWorks2016CTP3</u>	(F4=Prompt)	
Schema <u>Person</u>	(F4=Prompt)	
User Name <mark>rdbdemo</mark>		
Password	*****	
F1=Help F3=Exit F4=Prompt F6=Save F12=Return		
MA C		04/023

The example below is for a SQL Server configuration.

## DBURDBADD

To add a RDBWORKER job without having to restart the DBURDBSBS subsystem, execute the command **DBURDBADD**. One RDBWORKER job will be added each time the command is executed.

## DBURDB

To open a table on a remote database, enter the command DBURDB. By default, DBURDB will open the last table specified since this interactive session began. To open a different table, modify either of the first two parameters.

Type choices, press Enter.		
Table Name/Generic*/*ALL:	*PRV	
Remote Database ID:	*PRV	Character value, *ALL, *PRV
Default Format:	<u>*DBUAUT</u>	*DBUAUT, *SGL, *MLT
Default Mode:	*DBUAUT	*DBUAUT, *ADD, *CHG, *DSP
Print Audit Log:	*DBUAUT	*DBUAUT, *RQD, *ON
Allow Change of Table Name:	<u>*YES</u>	*YES, *NO
Revoke Add Authority:	<u>*NO</u>	*YES, *NO
Revoke Change Authority:	<u>*NO</u>	*YES, *NO
Revoke Delete Authority:	<u>*NO</u>	*YES, *NO
Number of Columns:	<u>0                                    </u>	0, 1, 2, 3
		5
	E12-01	Botton
F3=Exit F4=Prompt F5=Kerresh	FIZ=Cancel	FI3=HOW to use this display

**Table Name** – Enter the name of the table on the remote system. A generic value or the \*ALL may be entered here to retrieve a list of tables to open.

**Remote Connection** – The Remote Database ID that was created using **DBURDBCFG**. A generic value or the \*ALL may be entered here to retrieve a list of Remote Database IDs.